The Mikado

Opera A La Carte

CUES

Pre-show

CUE #1 **Function**: House UP; Warmers UP; Works UP

Channels: 48 **Level**: 40 **Function**: Curtain Warmers
Channels: 35 **Level**: 50 **Function**: Shoji Screen
Channels: 36,37 **Level**:100 **Function**: Blue Cyc

Pre-show

Function: House to HALF **Count**: 2

Pre-show

Function: House OUT **Count**: 2

Pre-show

CUE # 2 **Function**: Conductor Special UP **Count**: 2

Channel: 1 **Level**: 80 **Function**: Conductor Special

Page 14

CUE # 3 **Function**: Warmers OUT **Count**: 3

Channels: 48 **Level**: 0 **Function**: Curtain Warmers

CUE # 4 **Function**: Opening Wash **Count**: BUMP

Channel#	Level	(Change)	Function	Color	Position
1	(80)	N/C	Conductor Special	N/C	AP
2	80	+ 80	Front Pink	34	AP
8	80	+ 80	Front Pink	34	1E
3	90	+ 90	Front Lav	55	AP
9	90	+ 90	Front Lav	55	1E
4	50	+ 50	Front Blue	67	AP
5	80	+ 80	Pink Fill	34	Box Booms
6	90	+ 90	Lav Fill	55	Box Booms
7	50	+ 50	Blue Fill	67	Box Booms
16	70	+ 70	Blue Down	67	1E
17	70	+ 70	Blue Down	67	2E
18	70	+ 70	Blue Down	67	3E
19	80	+ 80	Amber Down	18	1E
20	80	+ 80	Amber Down	18	2E
21	80	+ 80	Amber Down	18	3E
22	60	+ 60	Magenta Down	46	1E
23	60	+ 60	Magenta Down	46	2E
24	60	+ 60	Magenta Down	46	3E
10	100	+100	High Side Fill	55	1E/SL
11	100	+100	High Side Fill	55	1E/SR
12	100	+100	High Side Fill	55	2E/SL
13	100	+100	High Side Fill	55	2E/SR
14	100	+100	High Side Fill	55	3E/SL
15	100	+100	High Side Fill	55	3E/SR
25,29			Bench Special	AP(01), AP(51), 2E(52)	
27,28			DC Special	AP(01), AP(51), 2E(52)	
26			DL Special	AP(01), AP(51), 1E(52)	
30			UC Arch	AP(01), AP(51)	
31,32			UC Arch	1E(01), 1E (51)	
33			UC Arch	3E(46)	
34			Red Arch	1E(27)	
35	100	+30	Shoji Screen	18	Floor Stands
36	100	+100	DAY BLUE	80	Cyc
37	100	+100	DARK BLUE	85	Cyc
38			RED	27	Cyc
39			Practical	N/A	SR lantern
40			Cloud	N/C	3E

Page 22

CUE # 5 **Function**: Arch Special UP (add to previous cue) **Count**: 2

Channels: 30,31,32,33 **Level**: 100 **Function**: UC Arch Special UP

Page 23

CUE # 6 **Function**: Restore Cue 4 (Arch Special OUT) **Count**: 5

Channels: 30,31,32,33 **Level**: 0 **Function**: UC Arch Special OUT

Page 31

CUE # 7 **Function**: Restore Cue 5 (Arch Special UP) **Count**: 2

Channels: 30,31,32,33 **Level**: 100 **Function**: UC Arch Special UP

Page 31

CUE # 8 **Function**: Restore Cue 4 (Arch Special OUT) **Count**: 5

Channels: 30,31,32,33 **Level**: 0 **Function**: UC Arch Special OUT

Page 41

CUE # 9 **Function**: Restore Cue 5 (Arch Special UP) **Count**: 4

Channels: 30,31,32,33 **Level**: 100 **Function**: UC Arch Special UP

Page 41

CUE # 10 **Function**: Restore Cue 4 (Arch Special OUT) **Count**: 5

Channels: 30,31,32,33 **Level**: 0 **Function**: UC Arch Special OUT

Page 51

CUE # 11 **Function**: Add DC Special UP (add to previous cue) **Count**: 5

Channels: 27,28 **Level**: 100 **Function**: DC Special UP

Page 54

CUE # 12 **Function**: Restore Cue 4 (DC Special OUT) **Count**: 7

Channels: 27,28 **Level**: 0 **Function**: DC Special OUT

CUE # 13 **Function**: Warmer **Count**: 5

Channel#	Level	(Change)	Function	Color	Position
1	(80)	N/C	Conductor Special	N/C	AP
2	100	+ 20	Front Pink	34	AP
8	100	+ 20	Front Pink	34	1E
3	70	- 20	Front Lav	55	AP
9	70	- 20	Front Lav	55	1E
4	(50)	N/C	Front Blue	67	AP
5	100	+ 20	Pink Fill	34	Box Booms
6	70	- 20	Lav Fill	55	Box Booms
7	(50)	N/C	Blue Fill	67	Box Booms
16	40	- 30	Blue Down	67	1E
17	40	- 30	Blue Down	67	2E
18	40	- 30	Blue Down	67	3E
19	100	+ 20	Amber Down	18	1E
20	100	+ 20	Amber Down	18	2E
21	100	+ 20	Amber Down	18	3E
22	90	+ 30	Magenta Down	46	1E
23	90	+ 30	Magenta Down	46	2E
24	90	+ 30	Magenta Down	46	3E
10	80	- 20	High Side Fill	55	1E/SL
11	80	- 20	High Side Fill	55	1E/SR
12	80	- 20	High Side Fill	55	2E/SL
13	80	- 20	High Side Fill	55	2E/SR
14	80	- 20	High Side Fill	55	3E/SL
15	80	- 20	High Side Fill	55	3E/SR
25,29			Bench Special	AP(01), AP(51), 2E(52)	
27,28			DC Special	AP(01), AP(51), 2E(52)	
26			DL Special	AP(01), AP(51), 1E(52)	
30			UC Arch	AP(01), AP(51)	
31,32			UC Arch	1E(01), 1E (51)	
33			UC Arch	3E(46)	
34			Red Arch	1E(27)	
35	(100)	N/C	Shoji Screen	18	Floor Stands
36	(100)	N/C	DAY BLUE	80	Cyc
37	(100)	N/C	DARK BLUE	85	Cyc
38			RED	27	Cyc
39			Practical	N/A	SR lantern
40			Cloud	N/C	3E

Page 69

CUE # 14 **Function**: DC Special UP (Add to Cue 13) **Count**: 3

Channels: 27,28 **Level**: 100 **Function**: DC Special UP

Page 75

CUE # 15 **Function**: Restore Cue 13 **Count**: 3

Channels: 27,28 **Level**: 0 **Function**: DC Special OUT

CUE # 16 **Function**: Cooler **Count**: 3

Channel#	Level	(Change)	Function	Color	Position
1	(80)	N/C	Conductor Special	N/C	AP
2	60	- 40	Front Pink	34	AP
8	60	- 40	Front Pink	34	1E
3	100	+ 30	Front Lav	55	AP
9	100	+ 30	Front Lav	55	1E
4	70	+ 20	Front Blue	67	AP
5	60	- 40	Pink Fill	34	Box Booms
6	80	+ 10	Lav Fill	55	Box Booms
7	70	+ 20	Blue Fill	67	Box Booms
16	80	+ 40	Blue Down	67	1E
17	(40)	N/C	Blue Down	67	2E
18	20	- 20	Blue Down	67	3E
19	60	- 40	Amber Down	18	1E
20	30	- 70	Amber Down	18	2E
21	10	- 90	Amber Down	18	3E
22	50	- 40	Magenta Down	46	1E
23	20	- 70	Magenta Down	46	2E
24	10	- 80	Magenta Down	46	3E
10	(80)	N/C	High Side Fill	55	1E/SL
11	(80)	N/C	High Side Fill	55	1E/SR
12	60	- 20	High Side Fill	55	2E/SL
13	60	- 20	High Side Fill	55	2E/SR
14	30	- 50	High Side Fill	55	3E/SL
15	30	- 50	High Side Fill	55	3E/SR
25,29			Bench Special	AP(01), AP(51), 2E(52)	
27,28			DC Special	AP(01), AP(51), 2E(52)	
26			DL Special	AP(01), AP(51), 1E(52)	
30			UC Arch	AP(01), AP(51)	
31,32			UC Arch	1E(01), 1E (51)	
33			UC Arch	3E(46)	
34			Red Arch	1E(27)	
35	(100)	N/C	Shoji Screen	18	Floor Stands
36	(100)	N/C	DAY BLUE	80	Cyc
37	(100)	N/C	DARK BLUE	85	Cyc
38			RED	27	Cyc
39			Practical	N/A	SR lantern
40			Cloud	N/C	3E

Page 91

CUE # 17 **Function**: Restore Cue 4 (with changes below) **Count**: 4

Channels: 2, 5, 8	**Level**: 100	**Function**: Pink wash up to FULL
Channels: 19, 20, 21	**Level**: 100	**Function**: Amber down wash up to FULL

Page 93

CUE # 18 **Function**: Restore Cue 16 (cooler) **Count**: 3

Page 104

CUE # 19 **Function**: Restore Cue 17 **Count**: 5

CUE # 20 **Function**: Katisha Entrance **Count**: BUMP

Channel#	Level	(Change)	Function	Color	Position
1	(80)	N/C	Conductor Special	N/C	AP
2	40	- 60	Front Pink	34	AP
8	40	- 60	Front Pink	34	1E
3	40	- 50	Front Lav	55	AP
9	40	- 50	Front Lav	55	1E
4	0	- 50	Front Blue	67	AP
5	40	- 60	Pink Fill	34	Box Booms
6	30	- 60	Lav Fill	55	Box Booms
7	0	- 50	Blue Fill	67	Box Booms
16	0	- 70	Blue Down	67	1E
17	0	- 70	Blue Down	67	2E
18	0	- 70	Blue Down	67	3E
19	40	- 60	Amber Down	18	1E
20	40	- 60	Amber Down	18	2E
21	40	- 60	Amber Down	18	3E
22	40	- 20	Magenta Down	46	1E
23	40	- 20	Magenta Down	46	2E
24	40	- 20	Magenta Down	46	3E
10	0	-100	High Side Fill	55	1E/SL
11	0	-100	High Side Fill	55	1E/SR
12	0	-100	High Side Fill	55	2E/SL
13	0	-100	High Side Fill	55	2E/SR
14	0	-100	High Side Fill	55	3E/SL
15	0	-100	High Side Fill	55	3E/SR
25,29			Bench Special	AP(01), AP(51), 2E(52)	
27,28			DC Special	AP(01), AP(51), 2E(52)	
26			DL Special	AP(01), AP(51), 1E(52)	
30	80	+ 80	UC Arch	AP(01), AP(51)	
31,32	80	+ 80	UC Arch	1E(01), 1E (51)	
33	80	+ 80	UC Arch	3E(46)	
34	100	+100	Red Arch	1E(27)	
35	(100)	N/C	Shoji Screen	18	Floor Stands
36	0	-100	DAY BLUE	80	Cyc
37	0	-100	DARK BLUE	85	Cyc
38	100	+100	RED	27	Cyc
39			Practical	N/A	SR lantern
40			Cloud	N/C	3E

Page 118

CUE # 21 **Function**: Moody / Warm and Evil-looking **Count**: 7

Channels: 2, 5, 8	**Level**: 60	**Function**: Front pink wash UP (20%)
Channels: 19, 20, 21	**Level**: 70	**Function**: Amber down wash UP (30%)
Channels: 22, 23, 24	**Level**: 80	**Function**: Magenta down wash UP (40%)
Channels: 21	**Level**: 20	**Function**: Amber down wash on 3E DOWN (20%)
Channels: 27, 28	**Level**: 80	**Function**: DC special
Channels: 34	**Level**: 0	**Function**: Red arch OUT

Page 125

CUE # 22 **Function**: Restore Cue 17 (with changes) **Count**: 10

Channels: 22,23,24	**Level**: 100	**Function**: Magenta down wash up to FULL
Channels: 19,20,21	**Level**: 50	**Function**: Amber down wash DOWN (50%)
Channels: 36,37	**Level**: TBD	**Function**: Restore Cyc to original blue wash

CUE # 23 **Function**: Lower Levels; DL Special UP **Count**: 7

Channel#	Level	(Change)	Function	Color	Position
1	(80)	N/C	Conductor Special	N/C	AP
2	60	- 40	Front Pink	34	AP
8	60	- 40	Front Pink	34	1E
3	40	- 50	Front Lav	55	AP
9	40	- 50	Front Lav	55	1E
4	20	- 30	Front Blue	67	AP
5	60	- 40	Pink Fill	34	Box Booms
6	40	- 50	Lav Fill	55	Box Booms
7	20	- 30	Blue Fill	67	Box Booms
16	40	- 30	Blue Down	67	1E
17	40	- 30	Blue Down	67	2E
18	40	- 30	Blue Down	67	3E
19	0	- 50	Amber Down	18	1E
20	0	- 50	Amber Down	18	2E
21	0	- 50	Amber Down	18	3E
22	40	- 60	Magenta Down	46	1E
23	40	- 60	Magenta Down	46	2E
24	40	- 60	Magenta Down	46	3E
10	40	- 60	High Side Fill	55	1E/SL
11	40	- 60	High Side Fill	55	1E/SR
12	40	- 60	High Side Fill	55	2E/SL
13	40	- 60	High Side Fill	55	2E/SR
14	40	- 60	High Side Fill	55	3E/SL
15	40	- 60	High Side Fill	55	3E/SR
25,29			Bench Special	AP(01), AP(51), 2E(52)	
27,28			DC Special	AP(01), AP(51), 2E(52)	
26	100	+100	DL Special	AP(01), AP(51), 1E(52)	
30			UC Arch	AP(01), AP(51)	
31,32			UC Arch	1E(01), 1E (51)	
33			UC Arch	3E(46)	
34			Red Arch	1E(27)	
35	(100)	N/C	Shoji Screen	18	Floor Stands
36	(100)	N/C	DAY BLUE	80	Cyc
37	(100)	N/C	DARK BLUE	85	Cyc
38			RED	27	Cyc
39			Practical	N/A	SR lantern
40			Cloud	N/C	3E

Page 130

CUE # 24 **Function**: Restore Cue 22 **Count**: 2

END OF ACT I - Page 139

CUE # 25 **Function**: FOH OUT (Except Conductor Special) **Count**: 2
DOUBLE CHECK FOR SPECIALS!

Channels: 2,3,4,5,6,7 **Level**: 0 **Function**: AP Front Wash and Box Booms OUT

END OF ACT I - Page 139

CUE # 26 **Function**: Blackout **Count**: BUMP

END OF ACT I - Page 139

CUE # 27 **Function**: House UP; Warmers UP; Works UP **Count**: 3

Channels: 48 **Level**: 40 **Function**: Curtain Warmers
Channels: 16,17,18 **Level**: 30 **Function**: Works (blue down wash) UP

ACT II

START OF ACT II - Page 140

House to HALF **Count**: 3

START OF ACT II - Page 140

House OUT **Count**: 2

START OF ACT II - Page 140

CUE # 28 **Function**: Conductor Special UP **Count**: 2

Channel: 1 **Level**: 80 **Function**: Conductor Special

Page 140

CUE # 29 **Function**: Warmers OUT, Works OUT **Count**: 3

Channels: 48 **Level**: 0 **Function**: Curtain Warmers OUT
Channels: 16,17,18 **Level**: 0 **Function**: Works (blue down wash) OUT

Page 140

CUE # 30 **Function**: Restore Cue 4 (with changes) **Count**: 4

Channels: 17 **Level:** 40 **Function**: Blue downs
Channels: 18 **Level:** 20 **Function**: Blue downs
Channels: 20 **Level:** 60 **Function**: Amber downs
Channels: 21 **Level:** 20 **Function**: Amber downs
Channels: 23 **Level:** 40 **Function**: Magenta downs
Channels: 24 **Level:** 20 **Function**: Magenta downs
Channels: 12,13 **Level:** 50 **Function**: Mid stage high sides
Channels: 14,15 **Level:** 25 **Function**: Upstage high sides
Channels: 35 **Level**: 0 **Function**: Shoji Screen Special OUT
Channels: 39 **Level**: 100 **Function**: Practical UP
Channels: 40 **Level**: 100 **Function**: Cloud UP

Page 158

CUE # 31 **Function**: DC Special UP **Count**: 3

Channels: 27,28 **Level**: 100 **Function**: DC Special

Page 163

CUE # 32 **Function**: Restore Cue 30 (DC Special OUT) **Count**: 2

Page 165

CUE # 33 **Function**: Restore Cue 4 (with changes) **Count**: 3

Channels: 22,23,24	**Level**: 100	**Function**: Magenta down wash UP
Channels: 35	**Level**: 0	**Function**: Shoji Screen Special OUT
Channels: 39	**Level**: 100	**Function**: Practical UP
Channels: 40	**Level**: 100	**Function**: Cloud UP

Page 167

CUE # 34 **Function**: Lav Front Wash UP; DC UP **Count**: 10

Channels: 3, 6, 9	**Level**: 100	**Function**: Lav Front Wash UP
Channels: 27,28	**Level**: 100	**Function**: Down Center UP

Page 172

CUE # 35 **Function**: DC OUT **Count**: 5

Channels: 27, 28	**Level**: 0	**Function**: Down Center OUT

Page 179

CUE # 36 **Function**: Bench Special UP **Count**: 5

Channels: 25,29	**Level**:100	**Function**: Bench Special

Page 196

CUE # 37 **Function**: Restore Cue 30 (with Lav Wash UP) **Count**: 5

Channels: 3, 6, 9 **Level**: 100 **Function**: Lav front wash UP

Page 204

CUE # 38 **Function**: Arch UP **Count**: 2

Channels: 30, 31,32,33 **Level**: 100 **Function**: Arch UP

Page 204

CUE # 39 **Function**: Bench UP; Arch OUT **Count**: 3

Channels: 25, 29 **Level**: 100 **Function**: Bench UP
Channels: 30, 31,32, 33 **Level**: 0 **Function**: Arch OUT

CUE # 40 **Function**: All Levels Lower; Bench Special UP **Count**: 7

Channel#	Level	(Change)	Function	Color	Position
1	(80)	N/C	Conductor Special	N/C	AP
2	30	- 50	Front Pink	34	AP
8	30	- 50	Front Pink	34	1E
3	30	- 70	Front Lav	55	AP
9	30	- 70	Front Lav	55	1E
4	20	- 30	Front Blue	67	AP
5	30	- 50	Pink Fill	34	Box Booms
6	30	- 70	Lav Fill	55	Box Booms
7	20	- 30	Blue Fill	67	Box Booms
16	0	- 70	Blue Down	67	1E
17	0	- 70	Blue Down	67	2E
18	0	- 70	Blue Down	67	3E
19	30	- 50	Amber Down	18	1E
20	30	- 50	Amber Down	18	2E
21	30	- 50	Amber Down	18	3E
22	30	- 70	Magenta Down	46	1E
23	30	- 70	Magenta Down	46	2E
24	30	- 70	Magenta Down	46	3E
10	30	- 70	High Side Fill	55	1E/SL
11	30	- 70	High Side Fill	55	1E/SR
12	30	- 70	High Side Fill	55	2E/SL
13	30	- 70	High Side Fill	55	2E/SR
14	30	- 70	High Side Fill	55	3E/SL
15	30	- 70	High Side Fill	55	3E/SR
25,29	(100)	N/C	Bench Special	AP(01), AP(51), 2E(52)	
27,28			DC Special	AP(01), AP(51), 2E(52)	
26			DL Special	AP(01), AP(51), 1E(52)	
30			UC Arch	AP(01), AP(51)	
31,32			UC Arch	1E(01), 1E (51)	
33			UC Arch	3E(46)	
34			Red Arch	1E(27)	
35			Shoji Screen	18	Floor Stands
36	(100)	N/C	DAY BLUE	80	Cyc
37	(100)	N/C	DARK BLUE	85	Cyc
38			RED	27	Cyc
39	(100)	N/C	Practical	N/A	SR lantern
40	(100)	N/C	Cloud	N/C	3E

CUE # 40.5 **Function**: DC UP (add to previous) **Count**: 5

Channels: 27,28 **Level**: 100 **Function**: DC OUT

CUE # 41 **Function**: Levels slightly higher; DC OUT **Count**: 3

Channel#	Level	(Change)	Function	Color	Position
1	(80)	N/C	Conductor Special	N/C	AP
2	60	+ 30	Front Pink	34	AP
8	60	+30	Front Pink	34	1E
3	90	+ 60	Front Lav	55	AP
9	90	+ 60	Front Lav	55	1E
4	40	+ 20	Front Blue	67	AP
5	60	+ 30	Pink Fill	34	Box Booms
6	90	+ 60	Lav Fill	55	Box Booms
7	40	+ 20	Blue Fill	67	Box Booms
16	(0)	N/C	Blue Down	67	1E
17	(0)	N/C	Blue Down	67	2E
18	(0)	N/C	Blue Down	67	3E
19	50	+ 20	Amber Down	18	1E
20	50	+ 20	Amber Down	18	2E
21	50	+ 20	Amber Down	18	3E
22	60	+ 30	Magenta Down	46	1E
23	60	+ 30	Magenta Down	46	2E
24	60	+ 30	Magenta Down	46	3E
10	70	+ 40	High Side Fill	55	1E/SL
11	70	+ 40	High Side Fill	55	1E/SR
12	70	+ 40	High Side Fill	55	2E/SL
13	70	+ 40	High Side Fill	55	2E/SR
14	70	+ 40	High Side Fill	55	3E/SL
15	70	+ 40	High Side Fill	55	3E/SR
25,29	(100)	N/C	Bench Special	AP(01), AP(51), 2E(52)	
27,28	0	-100	DC Special	AP(01), AP(51), 2E(52)	
26			DL Special	AP(01), AP(51), 1E(52)	
30			UC Arch	AP(01), AP(51)	
31,32			UC Arch	1E(01), 1E (51)	
33			UC Arch	3E(46)	
34			Red Arch	1E(27)	
35			Shoji Screen	18	Floor Stands
36	(100)	N/C	DAY BLUE	80	Cyc
37	(100)	N/C	DARK BLUE	85	Cyc
38			RED	27	Cyc
39	(100)	N/C	Practical	N/A	SR lantern
40	(100)	N/C	Cloud	N/C	3E

Page 212

CUE # 42 **Function**: Restore Cue 30; Pinks UP, Magentas UP **Count**: 2

Channels: 2,5,8 **Level**: 100 **Function**: Pink front wash UP
Channels: 22,23,24 **Level**: 100 **Function**: Magenta Down Wash UP

Page 221

CUE # 43 **Function**: Restore Cue 38; Amber DOWN **Count**: 5

Channels: 19,20,21 **Level**: 50 **Function**: Amber Down Wash DOWN (30%)

CUE # 44 **Function**: OMITTED

Page 222

CUE # 45 **Function**: Brighter **Count**: 2

Channels: 3,6,9 **Level**: 100 **Function**: Lav Front Wash to FULL
Channels: 4,7 **Level**: 100 **Function**: Blue Front Wash to FULL

Page 231

CUE # 46 **Function**: Silhouette **Count**: BUMP

Channels: 2-35**Level**: 0 **Function**: Everything OUT except Conducor, Cyc and Practical

Page 231

CUE # 47 **Function**: Black Out - except for Conductor **Count**: BUMP

THIS CUE IS OMITTED WHEN CURTAIN IS BEING BOUNCED!

Channels: 36, 37 **Level**: 0 **Function**: Cyc wash OUT
Channels: 39 **Level**: 0 **Function**: Practical OUT
Channels: 40 **Level**: 0 **Function**: Cloud OUT

Page 231

CUE # 48 **Function**: Conductor Special OUT **Count**: BUMP

Channels: 1 **Level**: 0 **Function**: Conductor Special

Page 231

CUE # 49 **Function**: Curtain Call **Count**: BUMP

Channels: 1-24 **Level**: 100 **Function**: Everything UP
Channels: 36,37 **Level**: 100 **Function**: Cyc Sky Blue
Channel: 39 **Level**: 100 **Function**: Practical

Page 231

CUE # 50 **Function**: FADE TO BLACK **Count**: 3

Page 231

CUE # 51 **Function**: Restore 27 (House UP; Warmers UP; Works UP) **Count**: 2

Channels: 48 **Level**: 40 **Function**: Curtain Warmers
Channels: 16,17,18 **Level**: 30 **Function**: Works (blue down wash) UP