The Gondoliers

Opera A La Carte

CUES

Pre-show

Preset House UP; Warmers UP; works UP

Pre-show

CUE # 1 **Function**: House to HALF **Count**: 2

Pre-show

CUE # 2 **Function**: Conductor Special UP **Count**: 2

Channel: 48 **Level**: 80 **Function**: Conductor Special

Pre-show

CUE # 3 **Function**: House OUT; Works OUT **Count**: 2

Page 9

CUE # 4 **Function**: Warmers OUT **Count**: 4

CUE # 5 **Function**: Opening Wash **Count**: 4

Channel#	Level	(Change)	Function	Color	Position
48	(80)	N/C	Conductor Special	N/C	AP
1	70	+70	Front Pink	34	AP
7	70	+70	Front Pink	34	1E
2	80	+80	Front Lav	55	AP
8	80	+80	Front Lav	55	1E
3	40	+40	Front Blue	67	AP
9	40	+40	Front Blue	67	1E
4	70	+70	Pink Fill	34	Box Booms
5	80	+80	Lav Fill	55	Box Booms
6	40	+40	Blue Fill	67	Box Booms
16	50	+50	Blue Down	67	1E
17	50	+50	Blue Down	67	2E
18	50	+50	Blue Down	67	3E
19	70	+70	Amber Down	18	1E
20	70	+70	Amber Down	18	2E
21	70	+70	Amber Down	18	3E
22	60	+60	Magenta Down	46	1E
23	60	+60	Magenta Down	46	2E
24	60	+60	Magenta Down	46	3E
10	70	+70	High Side Fill	55	1E/SL
11	70	+70	High Side Fill	55	1E/SR
12	70	+70	High Side Fill	55	2E/SL
13	70	+70	High Side Fill	55	2E/SR
14	70	+70	High Side Fill	55	3E/SL
15	70	+70	High Side Fill	55	3E/SR
25			Down Center	51(AP), 06(AP), 72(2E)	
26			Down Left	51(AP), 06(AP), 72(2E)	
27			Up Left	51(AP), 06(AP), 72(3E)	
28			Up Center	51(AP), 06(AP), 72(3E)	
29			Up Right (steps)	51(AP), 06(AP), 72(3E)	
30,31			Right Center	51(AP), 06(AP), 72(2E)	
32			Dias	51(1E), 06(AP)	
33,34	100	+100	Arcade/Palace	49(2E), 49(3E),83(2E),83(3E)	
35	100	+100	Clouds	N/C(3E)	
42,43,44	Bright Day	TBD	DAY BLUE	80, 85, 85	4E

Page 29

CUE # A **Function**: Gondola Cue A **Count**: 20

Gondola in from Up Right to Center (20 seconds)
(1 person)

Page 39

CUE # B **Function**: Gondola Cue B **Count**: 15

Gondola out from Center to Up Left (15 seconds)
(1 person)

Page 67

CUE # C **Function**: Gondola Cue C **Count**: 15

Gondola in from Up Left to Center
(5 people)

Page 67

CUE # 5.1 **Function**: Up Center Special UP (add to existing wash) **Count**: 5

Channels: 28 **Level**: 100 **Function**: Up Center

Page 67

CUE # 5.2 **Function**: Up Center Special OUT **Count**: 7

Channels: 28 **Level**: 0 **Function**: Up Center

CUE # 6 **Function**: Warmer **Count**: 5

Channel#	Level	(Change)	Function	Color	Position
48	(80)	N/C	Conductor Special	N/C	AP
1	100	+30	Front Pink	34	AP
7	100	+30	Front Pink	34	1E
2	100	+20	Front Lav	55	AP
8	100	+20	Front Lav	55	1E
3	(40)	N/C	Front Blue	67	AP
9	(40)	N/C	Front Blue	67	1E
4	100	+30	Pink Fill	34	Box Booms
5	100	+20	Lav Fill	55	Box Booms
6	(40)		Blue Fill	67	Box Booms
16	(50)	N/C	Blue Down	67	1E
17	(50)	N/C	Blue Down	67	2E
18	(50)	N/C	Blue Down	67	3E
19	100	+30	Amber Down	18	1E
20	100	+30	Amber Down	18	2E
21	100	+30	Amber Down	18	3E
22	80	+20	Magenta Down	46	1E
23	80	+20	Magenta Down	46	2E
24	80	+20	Magenta Down	46	3E
10	(70)	N/C	High Side Fill	55	1E/SL
11	(70)	N/C	High Side Fill	55	1E/SR
12	(70)	N/C	High Side Fill	55	2E/SL
13	(70)	N/C	High Side Fill	55	2E/SR
14	(70)	N/C	High Side Fill	55	3E/SL
15	(70)	N/C	High Side Fill	55	3E/SR
25			Down Center	51(AP), 06(AP), 72(2E)	
26			Down Left	51(AP), 06(AP), 72(2E)	
27			Up Left	51(AP), 06(AP), 72(3E)	
28			Up Center	51(AP), 06(AP), 72(3E)	
29			Up Right (steps)	51(AP), 06(AP), 72(3E)	
30,31			Right Center	51(AP), 06(AP), 72(2E)	
32			Dias	51(1E), 06(AP)	
33,34	(100)	N/C	Arcade/Palace	49(2E), 49(3E),83(2E),83(3E)	
35	(100)	N/C	Clouds	N/C(3E)	
42,43,44	Bright Day	N/C	DAY BLUE	80, 85, 85	4E

Page 86

CUE # 7 **Function**: UL Special UP; Areas Lower **Count**: 4

Channels: 27 **Level**: 100 **Function**: UL Special
Channels: 1,4,7 **Level**: 60 **Function**: Pink Front Wash
Channels: 2, 5, 8 **Level**: 60 **Function**: Lav Front Wash
Channels: 10 - 24 **Level**: 6 **Function**: High Sides and Down Washes

Page 87

CUE # 8 **Function**: UL Special OUT; DC Spec UP **Count**: 10

Channels: 27 **Level**: 0 **Function**: UL Special
Channels: 25 **Level**: 100 **Function**: DC Special

Page 87

CUE # 9 **Function**: DL Special UP **Count**: 4

Channels: 26 **Level**: 100 **Function**: DL Special

Page 89

CUE # 10 **Function**: DC Special OUT **Count**: 4

Channels: 25 **Level**: 0 **Function**: DC Special

Page 90

CUE # 11 **Function**: Restore Cue 5 (with RC Special UP) **Count**: 3

Channels: 30,31 **Level**: 100 **Function**: RC Special UP

Page 90

CUE # 11.1 **Function**: RC Special OUT **Count**: 5

Channels: 30,31 **Level**: 00 **Function**: RC Special OUT

Page 106

CUE # D **Function**: Gondola Cue D **Count**: 9

Gondola out from Center to Up Right (9 seconds)
(1 person)

Page 107

CUE # 12 **Function**: Restore Cue 6 (with UC Special UP) **Count**: 10

Channels: 28 **Level**: 100 **Function**: UC Special UP

Page 109

CUE # 12.1 **Function**: UC Special OUT **Count**: 5

Channels: 28 **Level**: 0 **Function**: UC Special OUT

CUE # 13 **Function**: Smaller areas, more DS **Count**:5

Channel#	Level	(Change)	Function	Color	Position
48	(80)	N/C	Conductor Special	N/C	AP
1	(100)	N/C	Front Pink	34	AP
7	70	-30	Front Pink	34	1E
2	(100)	N/C	Front Lav	55	AP
8	30	-30	Front Lav	55	1E
3	0	-40	Front Blue	67	AP
9	0	-40	Front Blue	67	1E
4	70	-30	Pink Fill	34	Box Booms
5	30	-70	Lav Fill	55	Box Booms
6	0	-40	Blue Fill	67	Box Booms
16	(50)	N/C	Blue Down	67	1E
17	20	-30	Blue Down	67	2E
18	0	-50	Blue Down	67	3E
19	(100)	N/C	Amber Down	18	1E
20	50	-50	Amber Down	18	2E
21	0	-100	Amber Down	18	3E
22	(80)	N/C	Magenta Down	46	1E
23	40	-40	Magenta Down	46	2E
24	0	-80	Magenta Down	46	3E
10	30	-40	High Side Fill	55	1E/SL
11	30	-40	High Side Fill	55	1E/SR
12	30	-40	High Side Fill	55	2E/SL
13	30	-40	High Side Fill	55	2E/SR
14	0	-70	High Side Fill	55	3E/SL
15	0	-70	High Side Fill	55	3E/SR
25			Down Center	51(AP), 06(AP), 72(2E)	
26			Down Left	51(AP), 06(AP), 72(2E)	
27			Up Left	51(AP), 06(AP), 72(3E)	
28			Up Center	51(AP), 06(AP), 72(3E)	
29			Up Right (steps)	51(AP), 06(AP), 72(3E)	
30,31			Right Center	51(AP), 06(AP), 72(2E)	
32			Dias	51(1E), 06(AP)	
33,34	(100)	N/C	Arcade/Palace	49(2E), 49(3E),83(2E),83(3E)	
35	(100)	N/C	Clouds	N/C(3E)	
42,43,44	Bright Day	N/C	DAY BLUE	80, 85, 85	4E

Page 153

CUE # 14 **Function**: Restore Cue 5 **Count**: 5

Page 154

CUE # E **Function**: Gondola Cue E **Count**: 20

Gondola in from Up Right to Center
(? people)

Page 160

CUE # F **Function**: Gondola Cue F **Count**: 15

Gondola out from Center to Up Left
(12 people)

Page 65

Page 160

CUE # 15 **Function**: FOH OUT **Count**: 4

Channels: 1-6 **Level**: 0 **Function**: Front Washes and Fill

END OF ACT I - Page 160

CUE # 16 **Function**: Black Out (Except Conductor Special) **Count**: BUMP

END OF ACT I - Page 160

CUE # 17 **Function**: Conductor Special OUT **Count**: BUMP

END OF ACT I - Page 160

CUE # 18 **Function**: House UP; Warmers UP; Works UP **Count**: 3

ACT II

START OF ACT II - Page 161

CUE # 19 **Function**:House to HALF **Count**: 3

START OF ACT II - Page 161

CUE # 20 **Function**: Conductor Special UP **Count**: 1

Channel: 1 **Level**: 80 **Function**: Conductor Special

START OF ACT II - Page 161

CUE # 21 **Function**: House OUT, Warmers OUT, Works OUT **Count**: 3

CUE # 22 **Function**: Act II Wash **Count**: 3

Channel#	Level	(Change)	Function	Color	Position
48	(80)	N/C	Conductor Special	N/C	AP
1	70	+70	Front Pink	34	AP
7	70	+70	Front Pink	34	1E
2	80	+80	Front Lav	55	AP
8	80	+80	Front Lav	55	1E
3	60	+60	Front Blue	67	AP
9	60	+60	Front Blue	67	1E
4	70	+70	Pink Fill	34	Box Booms
5	80	+80	Lav Fill	55	Box Booms
6	60	+60	Blue Fill	67	Box Booms
16	70	+70	Blue Down	67	1E
17	70	+70	Blue Down	67	2E
18	70	+70	Blue Down	67	3E
19	100	+100	Amber Down	18	1E
20	100	+100	Amber Down	18	2E
21	100	+100	Amber Down	18	3E
22	60	+60	Magenta Down	46	1E
23	60	+60	Magenta Down	46	2E
24	60	+60	Magenta Down	46	3E
10	100	+100	High Side Fill	55	1E/SL
11	100	+100	High Side Fill	55	1E/SR
12	100	+100	High Side Fill	55	2E/SL
13	100	+100	High Side Fill	55	2E/SR
14	100	+100	High Side Fill	55	3E/SL
15	100	+100	High Side Fill	55	3E/SR
25			Down Center	51(AP), 06(AP), 72(2E)	
26	100	+100	Down Left	51(AP), 06(AP), 72(2E)	
27			Up Left	51(AP), 06(AP), 72(3E)	
28			Up Center	51(AP), 06(AP), 72(3E)	
29			Up Right (steps)	51(AP), 06(AP), 72(3E)	
30,31			Right Center	51(AP), 06(AP), 72(2E)	
32	100	+100	Dias	51(1E), 06(AP)	
33,34			Arcade/Palace	49(2E), 49(3E),83(2E),83(3E)	
35			Clouds	N/C(3E)	
42,43,44	Deep Blue	TBD	DAY BLUE	80, 85, 85	4E

Page 180

CUE # 22.1 **Function**: Dias OUT **Count**: 5

Channels: 32 **Level**: 0 **Function**: Dias Special

Page 195

CUE # 23 **Function**: Magentas UP to FULL **Count**: 3

Channels: 22,23,24 **Level**: 100 **Function**: Magenta Down Wash

CUE # 24 **Function**: Dimmer **Count**: 4

Channel#	Level	(Change)	Function	Color	Position
48	(80)	N/C	Conductor Special	N/C	AP
1	(70)	N/C	Front Pink	34	AP
7	50	-20	Front Pink	34	1E
2	100	+20	Front Lav	55	AP
8	0	-80	Front Lav	55	1E
3	80	+20	Front Blue	67	AP
9	0	-60	Front Blue	67	1E
4	50	-20	Pink Fill	34	Box Booms
5	100	+20	Lav Fill	55	Box Booms
6	80	+20	Blue Fill	67	Box Booms
16	100	+30	Blue Down	67	1E
17	50	-20	Blue Down	67	2E
18	0	-70	Blue Down	67	3E
19	80	-20	Amber Down	18	1E
20	60	-40	Amber Down	18	2E
21	0	-100	Amber Down	18	3E
22	(60)	N/C	Magenta Down	46	1E
23	40	-20	Magenta Down	46	2E
24	100	-60	Magenta Down	46	3E
10	50	-50	High Side Fill	55	1E/SL
11	50	-50	High Side Fill	55	1E/SR
12	50	-50	High Side Fill	55	2E/SL
13	50	-50	High Side Fill	55	2E/SR
14	50	-50	High Side Fill	55	3E/SL
15	50	-50	High Side Fill	55	3E/SR
25			Down Center	51(AP), 06(AP), 72(2E)	
26	0	-100	Down Left	51(AP), 06(AP), 72(2E)	
27			Up Left	51(AP), 06(AP), 72(3E)	
28			Up Center	51(AP), 06(AP), 72(3E)	
29			Up Right (steps)	51(AP), 06(AP), 72(3E)	
30,31			Right Center	51(AP), 06(AP), 72(2E)	
32	0	-100	Dias	51(1E), 06(AP)	
33,34			Arcade/Palace	49(2E), 49(3E),83(2E),83(3E)	
35			Clouds	N/C(3E)	
42,43,44	Deep Blue	N/C	DAY BLUE	80, 85, 85	4E

Page 226

CUE # 25 **Function**: Restore 23 with UR Special UP **Count**: 5

Channels: 29 **Level**: 100 **Function**: UR Special

Page 231

CUE # 26 **Function**: UR Special OUT **Count**: 3

Channels: 29 **Level**: 0 **Function**: UR Special

Page 261

CUE # 27 **Function**: UR Special UP **Count**: 3

Channels: 29 **Level**: 100 **Function**: UR Special

Page 263

CUE # 27.1 **Function**: UR Special OUT **Count**: 5

Channels: 29 **Level**: 0 **Function**: UR Special

Page 264

CUE # 28 **Function**: Restore Cue 13 with changes **Count**: 10

Channels: 25 **Level**: 100 **Function**: DC Special UP
Channels: 35 **Level**: 0 **Function**: Clouds OUT
Channels: 45,46,47 **Level**: TBD **Function**: Keep Cyc Deep Blue
Channels: 33,34 **Level**: 0 **Function**: Palace/Arcades OUT

Page 265

CUE # 28.1 **Function**: UR Special UP **Count**: BUMP

Channels: 29 **Level**: 100 **Function**: UR Special UP

Page 266

CUE # 29 **Function**: Restore Cue 23 **Count**: 7

Page 277

CUE # 30 **Function**: Black Out - except for Conductor **Count**: BUMP

Channels: 1-47 **Level**: 0 **Function**: Everything OUT
Channels: 48 **Level**: 80 **Function**: Conductor Special

Page 277

CUE # 31 **Function**: Conductor Special OUT **Count**: BUMP

Channels: 48 **Level**: 0 **Function**: Conductor Special

Page 277

CUE # 32 **Function**: Curtain Call **Count**: BUMP

Channels: 1-24 **Level**: 100 **Function**: Everything UP
Channels: 1 **Level**: 100 **Function**: Conductor Special
CYC - SKY BLUE

Page 277

CUE # 33 **Function**: FADE TO BLACK **Count**: 4

Page 277

CUE # 34 **Function**: House UP; Warmers UP; Works UP **Count**: 2